



## PageFlip Image to Flash

Scan files into Page-flipping eBooks directly

### User Documentation

---

**Note: This product is distributed on a 'try-before-you-buy' basis. All features described in this documentation are enabled. The unregistered version will be added a demo watermark.**

## About PageFlip Image to Flash

Most people may have recognized that convert physical books into digital images, electronic text, or electronic books (e-books) by using a scanner becomes the easiest way to distribute books.

Flip book, as a new but flexible e-book type which combines page-flipping effect with electronic technology, is more and more popular in publishing world. The brand new publishing way radically changes how the 'common' people receive and view information. Normally by just clicking the page then readers can flip the page like reading real books on computers.

**PageFlip Image to Flash** is powerful software which combines most of features of flipbook generator. The program enables you to convert your image to multiple-features included page-flipping eBooks. You will find the tool is so useful to publish your books in a so fashion and popular way.

With using Image to Flipbook, you just need to add your images. The program provides you multiple image editing tools for you to optimize the scanned images before converting: de-skew, crop, flip, rotate, gray scale, and convert to B/W etc. You can also set page layout to impose images.

After editing the added images, you can define the output flipbook features then. In Flipping Book Design interface, you can set dozens of functionalities for your eBooks. For example you can change your flash book language, add passwords to protect your files, choose different flipbook templates, embed your brand images as backgrounds and so on.

PageFlip Image to Flash also provides different output methods for you to publish your flipping book: "HTML" is for publishing online, "ZIP" can be much easier for emailing, "EXE" is an intergraded format for quickly viewing, "Burn to CD" to output your digital books directly on CD-ROM.

## Detail features include:



- convert images to flash page-flipping eBooks.
- Output in 4 different formats: HTML, EXE, Zip and Burn to CD.

HTML allows you to upload to a website to be viewed online.

EXE and Zip allow you to send to your user by email to be viewed on their computer.

Burn to CD allows you to burn to disk so you can send out with physical media.

- Set page layout for added or scanned images.
- Provides multiple scan optimize tools before designing template: flip, rotate, de-skew, crop, convert to B/W, gray scale, etc.
- Output PDF format directly with define PDF properties, encryption, viewer and watermarks.
- Provide multiple templates with previewing effects instantly.
- Add encryption to protect created page-flipping eBooks.
- Insert background music, always play or define times.
- Set background color, image or flash.
- Define language for flash and set book reading from right to left (such as Arabic).
- Choose hard cover for eBooks.
- Customize toolbar buttons to set permissions for downloading, printing, sharing and more.
- Set colors for toolbar, book cover, book shadows, bookmarks and more.
- Set font color, type for windows and bookmarks.
- Set scale for zoom-in function in Classical and Spread templates.
- Export and save settings for future uses.

## Using PageFlip Image to Flash



## PageFlip Image to Flash


Scan files into Page-flipping eBooks directly

### User Documentation

---

PageFlip Image to Flash can be started either by launching the application via the desktop short cut, or directly from Windows Explorer.

Start the program, you will see the below initial window:



Besides creating flash eBooks, you can directly output scanned files to PDF format.

The instructions below will mainly introduce how to customize your style page-flipping book with ease based on scanning paper files.



## I. add images

### 1. Image


You can open Images from computer or digital camera:



Click this icon to choose Images from your computer or camera, or click "File->Add a Directory..." to add a folder of images together.

### 2. Reorder Images


Click "Action" in toolbar, then you will find different ways to reorder images:



#### (1) Move:

Choose the file you want to move, click "Action" to reorder the images: Move First, Move Up, Move Down and Move Last. Or directly drag the image to the position you want it to be.

#### (2) Sort:





There are four types of Sort method you can use to reorder images, by name/ file size/ image size/ create time.

### (3) Rearrange:

You can define paper order as some default mode or input order manually:

Rearrange paper order

Page range start From image: 1 To: 8

Mode

- ☒ Mode 1: 1,3,5,7,2,4,6,8
- ☐ Mode 2: 2,4,6,8,1,3,5,7
- ☐ Mode 3: 1,3,5,7,8,6,4,2
- ☐ Mode 4: 1,5,2,6,3,7,4,8
- ☐ Mode 5: 1,8,2,7,3,6,4,5
- ☐ Manual: 1,2,3,4,5,6,7,8

Rearrange Cancel

## 3. Optimize Images

If you want to optimize your images before converting to flipbook, there are many tools listed in "Image" drop-down list:



Here are some optimize interfaces:

**(1) Rotate:**





## PageFlip Image to Flash


Scan files into Page-flipping eBooks directly

### User Documentation

#### (2) Crop:



#### (3) De-skew:







#### (4) Convert to Black/White:



## 4. Output Settings

After optimizing images, you can define page layout or set other options for outputting flipbook or PDF.

#### (1) Output Quality:









## (2) Output Layout:

You can define how many pages to be imposed into a flipbook page or click "Custom" icon to set your wanted page columns and rows:



Or click "Customize..." to enter into "Setting" interface as below shows (You will be able to set Page size, orientation, margin, layout, position for the pages):






## PageFlip Image to Flash


Scan files into Page-flipping eBooks directly

### User Documentation

#### (3) Image Transform:



#### (4) Bookmark Settings (for outputting PDF files):





**(5) PDF Properties (for outputting PDF files):**

PDF Settings  
Page Settings  
Image Transform  
Bookmark  
PDF Additions  
Properties  
Security  
Viewer  
Watermark  
Input/Output  
Scan  
Email  
FTP

Add some metadata to your PDF (such as author, title, keywords and so on)

PDF information

Title:

Subject:

Author:

Keywords:

Default Settings OK Cancel

**(6) PDF Security (for outputting PDF files):**

PDF Settings  
Page Settings  
Image Transform  
Bookmark  
PDF Additions  
Properties  
Security  
Viewer  
Watermark  
Input/Output  
Scan  
Email  
FTP

Applying all of the encrypt options, what PDF encrypt policy do you want

Security Method:

☒ Add Security

☒ Require a password to open the document  
Document Open Password:

Permissions

☒ Use a password to restrict permissions  
Permissions Password:

Print Allowed:

Changes Allowed:

☐ Enable copying of content  
☐ Enable text access for screen reader devices for the visually impaired

Options

- ☒ Printing
- ☒ Changing the Document
- ☒ Allow Content Copying or Extraction
- ☒ Authoring Comments and Form Fields
- ☒ Allow Form Field Fill-in or Signing
- ☒ Content Accessibility Enabled
- ☒ Document Assembly

Default Settings OK Cancel




## PageFlip Image to Flash


Scan files into Page-flipping eBooks directly

### User Documentation

#### (7) PDF Viewer (for outputting PDF files):



#### (8) PDF Watermark (for outputting PDF files):





## PageFlip Image to Flash

Scan files into Page-flipping eBooks directly

### User Documentation

#### (9) Scan Settings:


The screenshot shows the 'Scan Settings' dialog box. On the left is a tree view with categories: PDF Settings, Page Settings, Image Transform, Bookmark, PDF Additions, Properties, Security, Viewer, Watermark, Input/Output, Scan (selected), Email, and FTP. The main area is titled 'Scan settings' and contains several options: an 'Enable' checkbox, checkboxes for 'FileTransfer', 'CompatibilityMode', 'UseMemoryHandle', and 'Buffered transfer', and a 'Log Scan' checkbox with an adjacent text field. Below these is a 'Scan Support' section with radio buttons for 'Twain' (selected) and 'Wia'. At the bottom are checkboxes for 'Save last settings' (checked) and 'Delete last image (If the scanner always scan a extra image)'. A yellow information box on the right explains the 'FileTransfer' property, listing three methods: native transfer, buffered transfer, and file transfer. It also notes that 'CompatibilityMode' disables capability setting and reading, and that some scanner drivers do not support memory handles. The dialog has 'Default Settings', 'OK', and 'Cancel' buttons at the bottom.

#### (10) Email Settings (for outputting PDF files and Email directly):

The screenshot shows the 'Email Settings' dialog box. The left tree view is identical to the previous dialog, with 'Email' selected under the 'Input/Output' category. The main area is titled 'Automatically attach output PDF to an email after the printing finishes' and features an email icon. It contains a 'Send Email' section with input fields for 'Recipients', 'Subject', and 'Email Body'. Below this is an 'Attachment name' field with the text 'Attachment'. The dialog has 'Default Settings', 'OK', and 'Cancel' buttons at the bottom.



**(11) FTP Settings (for outputting PDF files and FTP instantly):**



**5. Output**

Choose output as "Build Flipbook" to enter into template setting interface:








## PageFlip Image to Flash

Scan files into Page-flipping eBooks directly

## User Documentation

## II. Template Settings


Below image is the overview for the Template Settings interface:



The design setting interface contains below main parts: Choose Template; Book; Sound; Tool Bar; Bookmark; Initial Show; Links; Language; Security Settings; Font.

### 1. Choose Template




Click  icon to select templates from below interface:



## PageFlip Image to Flash

Scan files into Page-flipping eBooks directly

### User Documentation



Click this icon is to save current settings as a TXT file for later uses;



Click this icon is to import stored setting file at once.

## 2. Book Panel

|                           |              |
|---------------------------|--------------|
| Book                      |              |
| Book Title                | www.FlipB... |
| Hide Book Frame Bar       | No           |
| Retain the book to center | No           |
| Book Proportions          |              |
| Top Margin                | 10           |
| Bottom Margin             | 10           |
| Left Margin               | 60           |
| Right Margin              | 60           |
| Flash Window Color        | 0x021A25     |
| Page Background Color     | 0xffffffff   |
| Page Shadow               |              |
| Background Config         |              |
| Right To Left             | No           |
| Hard Cover                | No           |
| Flipping Time             | 0.6          |



**(1) Book Title (only can be set in Float Template)**




Customize book title for showing on the top of your flipbook.

**(2) Hide Book Frame Bar**




If don't want to show the book frame bar, choose "Yes" in this option.

**(3) Retain the book to center**



If you select "No" in this option, the eBook will be shown on the right-side. This setting is for embedding special background image, such as advertisement or company log.

**(4) Book Proportions**




Please note that the values are not fixed in pixels or inches, they just represent a ratio for "Page Width: Page Height", and the book size will be changed depend on your Explorer Window Size.



## (5) Book Margin

A. Book Margin (set in Classical Template):



"Book Margin" refers to the distance between the book and the toolbar.

B. Top/ Bottom/ Left/ Right Margin (set in Float/ Spread Template):



## (6) Flash Window Color



This color will be applied on all flash windows, such as the book window, "Help" window, "Print" window and so on.



## PageFlip Image to Flash

Scan files into Page-flipping eBooks directly

### User Documentation

#### (7) Icon Color (only in Classical Template)




#### (8) Page Background Color



When load pages, or if the page number of your PDF file is odd, then the page (the last page) will show with the "Page Background Color".

#### (9) Page Shadow



The value also takes the value of Book Proportions as reference, and the value interval of "Page Shadow Opacity" is "0~1", the larger value refers to the deeper shadow color.

#### (10) Background Config

A. Background Color:




## PageFlip Image to Flash

Scan files into Page-flipping eBooks directly


### User Documentation

---




Define background for your flipbook with gradient color or pure color (the same color for "Gradient Color A" and "Gradient Color B"). Gradient Angle is the angle between the two colors.

#### B. Background Image setting in Classical and Spread templates:



Click the icon "..." to choose background image from your computer, and there are 11 kinds of "Image Position" for you to choose: Scale to fit, Fill, Top Left, Top Center, Top Right, Middle Left, Middle Center, Middle Right, Bottom Left, Bottom Center and Bottom Right.

#### C. Background Image setting in Float template:



The Float template enables you to add two background images: Outer Image and Inner Image. You can make Inner background image to show special information, such as advertisement or company logo, etc. There are also 11 kinds of "Image Position" for you to choose: Scale to fit, Fill, Top Left, Top Center, Top Right, Middle Left, Middle Center, Middle Right, Bottom Left, Bottom Center and Bottom Right.





### (11) Right to Left

If the language of your file is read from right to left (such as Arabic), then choose "Yes" in "Right to Left" option:



### (12) Hard Cover

If you want create hard cover effect (a book bound with rigid protective covers) for your flipbook, choose "Yes" in "Hard Cover" option:



### (13) Flipping time

|               |     |
|---------------|-----|
| Flipping Time | 0.6 |
|---------------|-----|

 Sets page flipping time in seconds according to your needs.  
(Recommended second value is 0.6)

## 3. Sound Panel





# PageFlip Image to Flash

Scan files into Page-flipping eBooks directly

## User Documentation

If you want to add background sound to your flipbook, such as a song or other audio file, set "Enable Sound->Enable", then click "🔊" icon to choose "Sound File" from your computer, then set "Sound Loops", "-1" stands for playing the sound file all the time while viewing flipbook, other value (N>0) stands for the times of playing the sound file.

### 4. Tool Bar

|                             |              |
|-----------------------------|--------------|
| ☐ Tool Bar                  |              |
| Tool bar                    | Show         |
| Bar Color                   | ■ 0x000000   |
| Icon Color                  | □ 0xffffffff |
| ☑ Zoom Config               |              |
| Print Enable                | Yes          |
| ☑ Download setting          |              |
| Full Screen Button          | Show         |
| Full Screen Without Tool... | No           |
| Help Button                 | Show         |
| ☑ Share Button              |              |
| ☑ Auto Flip                 |              |


#### (1) Tool bar (only in Classical Template)

|          |      |
|----------|------|
| Tool bar | Show |
|----------|------|

Show or Hide Tool bar in created flipbook.

#### (2) Zoom Config

|                |     |
|----------------|-----|
| ☑ Zoom Config  |     |
| Zoom in enable | Yes |
| Zoom Scale     | 1.5 |



To Enable Zoon In functionality, choose "Yes" in "Zoon in enable", then set "Zoom Scale", the value is the times between zoomed page size and the current page size.



### (3) Print Enable

|              |     |
|--------------|-----|
| Print Enable | Yes |
|--------------|-----|

Choose "Yes" in "Print Enable", then click icon  to set print page range as below:




A screenshot of a 'Print' dialog box. It has three radio button options: 'Print All Pages' (selected), 'Print Current Page', and 'Print Range'. Below the 'Print Range' option is a text input field with the example text 'Example: 2, 5, 8-26'. At the bottom right is a 'Print' button.

### (4) Download setting

|                  |             |
|------------------|-------------|
| Download setting |             |
| Download Enable  | Yes         |
| Download URL     | PDFDemo.pdf |



If you want your flipbook readers to download the PDF file or the flipbook directly from your website, select "Yes" in "Download Enable" option, then input the Download URL directly, you can use absolute path like "http://www.flipbuilder.com/flip-pdf/example/files/download/FlipPDFDemo.pdf" or relative path like "/files/download/FlipPDFDemo.pdf" (make sure you have uploaded the PDF to the same path).

Then readers can click the icon  to download your uploaded PDF file directly.

### (5) Full Screen

To enable "Full Screen" functionality in output flipbook, select "Show" in "Full Screen Button" option:

|                    |      |
|--------------------|------|
| Full Screen Button | Show |
|--------------------|------|

Then you can click icon  to view flipbook in Full Screen, click icon  or "Esc" button to exit from the Full Screen.

Or if you want to show your flipbook without Tool Bar while showing in Full Screen mode, you can set "No" in "Full Screen without Tool Bar" (just in Classical Template):

|                             |     |
|-----------------------------|-----|
| Full Screen Without Tool... | Yes |
|-----------------------------|-----|




## (6) Help Button

To show tips about viewing flipbook, you can set "Show" in "Help Button" option:

|             |      |
|-------------|------|
| Help Button | Show |
|-------------|------|


Then you can see the button  and click to get the tips as below:




## (7) Share Button

If you want your flipbook viewers to send the link to their friends or clients, you can add a share button in your flipbook for readers to send out your flipbook link immediately:

|                                       |               |
|---------------------------------------|---------------|
| <input type="checkbox"/> Share Button |               |
| Share Button                          | Show          |
| Email Subject                         | Rear my fi... |
| Email Body                            | {link}        |

When the viewers click the share button , they will enter into the Email interface with the link of your flipbook in the Email body.

## (8) Auto Flip

To auto flip your eBooks, you can set "Yes" in "Auto Flip->Enable" option; then define the Flip Interval (seconds of staying on each page); the value of "Play Count" stands for the times of auto playing the eBook, and "-1" stands for playing forever (after clicking the Auto Flip button , the flipbooks will be flipped by staying 3 seconds per page); if you want to auto start and flip the eBook after opening, just set "Auto flip when start up->Yes":

|                                    |     |
|------------------------------------|-----|
| <input type="checkbox"/> Auto Flip |     |
| Enable                             | Yes |
| Flip Interval                      | 3   |
| Play Count                         | -1  |
| Auto flip when start up            | Yes |



# PageFlip Image to Flash

Scan files into Page-flipping eBooks directly

## User Documentation


### 5. Initial Show (set in Float/ Spread Template)

You can show Bookmark panel or Thumbnails panel on the flash page at the beginning, just select "Bookmark" or "Thumbnails" in this option:


For Example, select "Thumbnails":



Then you will get flipbook shown with below initial interface:



### 6. Bookmark




In "Design Setting" panel (only in Classical Template, in other templates, the colors will be adjusted automatically based on your defined flash window color), you can set "Font color", "Background color",



"Background alpha" (refers to the background opacity, value interval: 0~1, "0" stands for the background is totally transparent), "Always Show Bookmark->True/ False" and "Panel Position->Left/ Right".

In "Bookmark" panel, if you didn't check "Import bookmark" option in "Import PDF" interface, or you want to create new bookmarks for your flipbook, you can add bookmarks even sub-bookmarks here, click "Add" icons and then input "Title" and "Page".

When click the bookmark button , it will popup the bookmark panel immediately, and click on those bookmarks, it will jump to the defined page automatically

## 7. Language




You can set language for showing tools or tips in your created flipbook, and here is the specialized instruction page for setting the "Language Option".

## 8. Security Settings



If you want to protect your flash books with passwords, you can click "..." icon to enter into "Flash Security Config" interface:



Select "Security Type->Single Password", and input passwords into the box (there is no restriction on password format at present). You can also set "Protect Page Range" as "All Pages" or the latter pages after a defined page number. (Tips: The program utilize RC4 algorithm to protect eBook pages, the eBook content pages will show nothing without permission.)






## 9. Font



If you want to change fonts of toolbar buttons, flash windows even bookmarks, you can set font types and colors in Font Panel.

## 10. Language Options Interface

Click "Option->Flash Language", you will enter into the Language Settings interface as below shows:






As the tips explaining, the "Labeled" column lists the buttons and instructions on Flash books in defined language, and the program provides you five different languages for you to use: English, Chinese Arabic, French and Greek.




You can also add other language for your own uses:

- (1). Click the button  and define name for the new language:



Click "OK" to save the new language in the list;

- (2). Choose the first label and click "Edit" icon, define new language text in "Labeled" box, then click "Save And Edit Next":






(3). At last, you can get all Labels translated into your new language as the images shows:

| Label                     | Labled                |
|---------------------------|-----------------------|
| First Button              | Première              |
| Next Page Button          | Page suivante         |
| Last Button               | Dernière              |
| Previous Page Button      | Page précédente       |
| Download Button           | Télécharger           |
| Print Button              | Imprimer              |
| Search Button             | Rechercher            |
| Book Mark Button          | Réservez Mark         |
| Help Button               | Aide                  |
| Enable FullScreen Button  | Activer FullScreen    |
| Disable FullScreen Button | Désactiver FullScreen |
| Sound On Button           | Le Sound              |


You can delete unwanted language:



Or save your edited new language file as XML or TXT file:



Load language file saving before for current using:



After setting template and language, click




icon to apply the settings.



## IV. Output Interface

Click "Convert To Flipping Book" button to enter into output option interface:



### 1. HTML



This output type is for uploading created page-flipping ebook onto websites:

You can define HTML Title and other properties by clicking "Advanced" button:




Set Keywords, Description or even Script in the below interface:




## PageFlip Image to Flash

Scan files into Page-flipping eBooks directly

### User Documentation




You will get a single folder "My Flash" under your defined path, open it to view "My Flash.html file" online:



If you want to show the Flash file on your website, make sure upload all these files under a same FTP path.

## 2. ZIP



This output type is for compressing the created files into an integral ZIP package which can be sending out as attachment directly. You can define HTML Advanced Settings by clicking "Advanced" icon: 

Your recipients just need to uncompress the ZIP file and then they can view the HTML flipbook instantly:







### 3. EXE




This type is for outputting flipbook as a single executive file, easy storing and easy viewing:




You can also define Icon and Opening Window Size in Advanced Settings:



You can even burn the output flipbook to CD:



After choosing output type, then check the option "Burn to CD", set "CD Writer", define "Disc title", at last click  button to output flipbook in your defined type.





## **At Last**

PageFlip Image to Flash is very useful software when you want to find an interest and easy way to show your physical books online. If you want to catch people's attention, just use this great program to turn dull text and images into a gorgeous flip book. Try this amazing handy tool to create funny flipping books, you will love it...

Now, use PageFlip Image to Flash to produce your style stunning page-flipping eBooks.

For more information: <http://www.pageflippdf.com>